

# How do I turn off the event messages in SLIC

By default, SLIC will print out markers for the beginning and end of events as they are simulated.

```
>>>> BeginEvent <1>  
>>>> EndEvent <1>
```

To turn off these messages, e.g. if you are generating a large number of events and want to reduce the log file size, the following two lines should be added to your SLIC macro.

```
/log/PrimaryGeneratorAction/setLogLevel 0  
/log/EventAction/setLogLevel 0
```

The first command turns off "BeginEvent" and the second disables "EndEvent".